



Script “iqstreamcncr”


Description:

The script "iqstreamcncr" allows the user to setup and start IQ streams by using signalshark SCPI commands.


When the script executes, it asks the user to enter the IP address of the PC, and then the CBW of the IQ stream. The script then allows the signalshark device to establish its connection with the PC and start the IQ stream. Additionally, the script saves the CBW and the IP address of the PC in the iqstreamcncr.json file in the project directory for later referencing.

Procedure


1. Open the Narda Script Launcher application and select the "nsltools" tab.
2. Select the script "IQ Stream Control".




3. When the script executes, it asks the user to enter the IP address of the PC:




4. Enter the IQ streaming bandwidth in the next dialog:



5. The script will save the IQ CBW and the PC IP address in a json file in the project directory and terminate automatically.



6. If the connection with the PC fails for any reason (e.g. if the entered IP address of the PC is wrong, etc.), the script will terminate giving an initialization error:



7. Press "Ok" to terminate the script and restart with the correct IP address and CBW inputs.

Narda Safety Test Solutions GmbH
 Sandwiesenstrasse 7
 72793 Pfullingen, Germany
 Phone +49 7121 97 32 0
 info.narda-de@L3Harris.com

L3Harris Narda STS
 North America Representative Office
 435 Moreland Road
 Hauppauge, NY11788, USA
 Phone +1 631 231 1700
 NardaSTS@L3Harris.com

Narda Safety Test Solutions S.r.l.
 Via Rimini, 22
 20142 Milano, Italy
 Phone +39 0258188 1
 nardait.support@L3Harris.com

Narda Safety Test Solutions GmbH
 Beijing Representative Office
 Xiyuan Hotel, No. 1 Sanlihe Road,
 Haidian
 100044 Beijing, China
 Phone +86 10 6830 5870
 support@narda-sts.cn

www.narda-sts.com

© Names and Logo are registered trademarks of Narda Safety Test Solutions GmbH and L3Harris Technologies, Inc. - Trade names are trademarks of the owners.