



Script “signalsharkwol”



Description:

The script "signalsharkwol" allows the user to wake up a SignalShark 3320/3330 device on LAN by sending a UDP broadcast message. SignalShark 3310 handheld devices do not support WoL.


When the script executes, it prompts the user to enter the IPv4 UDP broadcast address first. Then it prompts the user to enter the 6-byte MAC address of the signalshark that the user intends to wake-up-on-LAN (WoL). The script uses the WoL port 4000 to send the broadcast message with the MAC address enclosed.

Procedure

1. Open the Narda Script Launcher application and select the "nsltools" tab.
2. Select the script "SignalShark WOL".
3. Enter the UDP broadcast address in the pop-up dialog:



4. Enter the MAC address of the signalshark device that needs to be woken up:



5. Press "Ok" to send the UDP broadcast message with the MAC address and terminate the script.

Narda Safety Test Solutions GmbH
 Sandwiesenstrasse 7
 72793 Pfullingen, Germany
 Phone +49 7121 97 32 0
 info.narda-de@L3Harris.com

L3Harris Narda STS
 North America Representative Office
 435 Moreland Road
 Hauppauge, NY11788, USA
 Phone +1 631 231 1700
 NardaSTS@L3Harris.com

Narda Safety Test Solutions S.r.l.
 Via Rimini, 22
 20142 Milano, Italy
 Phone +39 0258188 1
 nardait.support@L3Harris.com

Narda Safety Test Solutions GmbH
 Beijing Representative Office
 Xiyuan Hotel, No. 1 Sanlihe Road,
 Haidian
 100044 Beijing, China
 Phone +86 10 6830 5870
 support@narda-sts.cn

www.narda-sts.com

® Names and Logo are registered trademarks of Narda Safety Test Solutions GmbH and L3Harris Technologies, Inc. - Trade names are trademarks of the owners.